





Hooked



RIBBONXL



Rock Steady Festival-Pouch *Another Free Pattern by Hooked*



Abbreviations:

- ch = chain
- ss = slip stitch
- dc = double crochet
- tr = trebles
- *..* = repeat

What you need:

- left overs (in total max. 200 grs) in 3 colour of of RibbonXL
- We used 1. Early Dew, 2. Pearl White and 3. Stone Grey
- 10 mm crochet hook
- 1 Clutch Quality Jasseron chain
- tapestry needle
- magnetic button



Scan this QR code to see our tutorials for basic stitches on Youtube




This pattern is suitable for medium- advanced crocheters. If you are a novice crocheter we recommend you to first try out the stitches with our videos.

- 1 Chain 21
2. Make a turning chain and crochet in each stitch of the chain, until you return to the first chain stitch (21). In this first chain stitch, make 3 double crochets in the same stitch, allowing you to continue on the other side of the chain stitch. Proceed until you have gone all the way around. This is shown in the diagram below.



- 3-5. You continue to crochet round about in spiral in colour nr 1 (RibbonXL early dew, close the last stitch with a ss, whilst changing colour (ribbonxl pearl white).
6. crochet round about dc in white, close with ss, whilst changing into colour 3 (Ribbonxl Stone Grey).
7. crochet round about dc, close with ss, whilst changing into colour 1
- 8-9. crochet round about in dc, and close with ss, whilst changing into colour 2 (white).
- 10-12. crochet round about whilst interchanging colours 2 and 3 every 3rd stitch. Use the diagram on the right to anticipate the colour changes. Switch colour whilst finishing, each 3rd stitch, yarn over and pull the new colour through the loop. Continue to crochet round, changing the colour every 3rd stitch, while carrying the previously crocheted yarn (see images tapestry crochet). Close the last stitch in the round, whilst changing back into colour 1



13. crochet round in dc and finish with a ss.

Important note: This Hooked pattern is offered to you for free and is written in UK English by non-native speakers. Use the conversion table below to check the required stitches in Dutch, German or US-English. Suggestions are welcome!

SYMBOL	NL	DE	UK	US
0	Losse (l)	Luftmasche (Lm)	Chain (ch)	Chain (ch)
&	Halve vaste (hv)	Kettmasche (Km)	Slip stitch (sc)	Slip stitch (sl st)
!	Vaste steek (v)	Feste Masche (fM)	Double crochet (dc)	Single crochet (sc)
@	Half stokje (hst)	Halbes Stäbchen (hStb)	Half treble crochet (htr)	Half double crochet (hdc)
2	Stokje (stk)	Stäbchen (Stb)	Treble crochet	Double Crochet (dc)
3	Dubbel stokje(dtsk)	Doppelstäbchen (DStb)	Double Treble (dtr)	Treble Crochet (tr)

Sew on the clutch quality jasseron chain with the tapestry needle using some excess thread in colour 1. Then sew the magnetic buttons on the inside of the bag with a needle and matching thread. Fasten off and neaten. Now you are ready to rock!

Share your creations with us. We'd love to see what you've made. xxx
www.hooked.nl

